

Herbjes

Step-by-step guide



WATCH OUR
VIDEO GUIDE

The Easiest and Most Efficient Method to Germinate Cannabis Seeds in Germination Kit



What You'll Need

- Cannabis seeds
- Germination paper (2 sheets)
- Clean water (distilled, rainwater, or bottled potable water)
- Germination container
- Spray bottle and included pipette

Optimum Conditions for Germination

- **Temperature:** 22-27°C (72-80°F)
- **Humidity:** 70-90%
- **Light:** Keep seeds in complete darkness
- **Airflow:** Ensure light airflow, but avoid direct drafts

Step 1. Prepare the Germination Paper



Place one dry sheet of germination paper at the bottom of the container.



Moisten the paper with clean, pH-neutral water. The water should be warm, ideally 28-32°C (82-90°F). Using the included pipette, measure out 3 ml (0.1 fl oz) of water and gently distribute it over the paper. Avoid overwatering.



TIPS:

- Avoid using tap water, even if it has been dechlorinated, as it may negatively affect germination.
- The paper should be evenly moist, but not dripping.

Step 2. Place the Seed



Carefully place the cannabis seed on the paper using clean hands or clean tweezers.



Gently cover the seed with the second sheet of germination paper.



Using the included pipette, add another 3 ml (0.1 fl oz) of water to moisten the top sheet.



Close the container.

Step 3. Store in a Dark Place



Store the container in a dark, warm location with an ambient temperature of 22-27°C (72-80°F), such as a kitchen cabinet, cupboard, or drawer.


Step 4. Monitor the Seeds



Check the seed after the first 12-24 hours, then every 6-12 hours. Keep the paper consistently moist, but do not overwater.

Germination typically occurs within 36-48 hours, although some seeds may take up to 7 days.

Step 5. Transplant the Germinated Seed



Once the taproot reaches 5-10 mm (3/16-3/8 inch) in length, carefully transplant the seed into your chosen growing medium (soil, coco, etc.).



Place the seed into a small hole with the taproot facing downward and lightly cover it with soil.



Moisten the surface using a few gentle sprays from a spray bottle.



To maintain humidity, you can loosely cover the pot with a plastic bag or plastic wrap, or place a plastic cup over the planted seed until it sprouts.

The first sprouts typically appear within 1-3 days.

Final Notes

By following these steps, you create an ideal environment for your seeds to germinate, ensuring a strong and healthy start for your plants.

** If the seed has not sprouted within 7 days, please contact our consultant for assistance.*

Herbies Head Shop does not support or encourage the use, production, or supply of illegal substances. For more information, please refer to our [Legal Disclaimer](#).

Helpful Links for Growers

Here are some great resources to dive deeper into growing tips, tricks, and more. Check them out and keep your cultivation game strong!

Quiz: Pick Yourself the Perfect Beginner Strain



Best Cannabis Strains for Beginner Growers



Easy-to-Grow Strains



Strains for Beginners



Blog Articles for Beginners

How to Quickly and Successfully Germinate Cannabis Seeds



Planting Germinated Cannabis Seeds The Right Way



*Click on the links to find out more

